User's Manual

AQ1100A, AQ1100B, AQ1100D OLTS Multi Field Tester Communication Interface



Thank you for purchasing the AQ1100A, AQ1100B, and AQ1100D OLTS Multi Field Tester. This Communication Interface User's Manual describes the functions and commands of the following communication interfaces.

- USB Interface
- Ethernet Interface (Optional)

To ensure correct use, please read this manual thoroughly before beginning operation.

After reading the manual, keep it in a convenient location for quick reference whenever a question arises during operation.

The following manuals are provided for the AQ1100A, AQ1100B, and AQ1100D. Please read all of them.

Manual Name	Manual No.	Description
AQ1100A, AQ1100B, AQ1100D OLTS Multi Field Tester User's Manual (CD-ROM)	IM AQ1100-01EN	Explains all functions except for the communications functions and operation procedures of the instrument.
AQ1100A, AQ1100B, AQ1100D OLTS Multi Field Tester Communication Interface User's Manual (CD-ROM)	IM AQ1100-17EN	Describes the communications functions of the USB/Ethernet interfaces. This manual.
AQ1100A, AQ1100B, AQ1100D OLTS Multi Field Tester Operation Guide	IM AQ1100-02EN	Describes safety precautions and the basic operations.

Notes

- The contents of this manual are subject to change without prior notice as a result of improvements in instrument's performance and functions.
- Every effort has been made in the preparation of this manual to ensure the accuracy of its
 contents. However, should you have any questions or find any errors, please contact your nearest
 YOKOGAWA representative.
- Copying or reproduction of all or any part of the contents of this manual without YOKOGAWA's permission is strictly prohibited.

Trademarks

- Microsoft, Windows, Windows XP and Windows Vista are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.
- · Adobe, Acrobat, and PostScript are trademarks of Adobe Systems Incorporated.
- In this manual, the TM and ® symbols do not accompany their respective registered trademark or trademark names.
- Other company and product names are registered trademarks or trademarks of their respective holders.

Revisions

November 2009: 1st Edition
December 2015: 2nd Edition
October 2017: 3rd Edition

3rd Edition : October 2017 (YMI)

All Rights Reserved, Copyright © 2009 Yokogawa Electric Corporation

All Rights Reserved, Copyright © 2017 Yokogawa Test & Measurement Corporation

IM AQ1100-17EN

How to Use this Manual

Structure of the Manual

This User's Manual consists of the following sections:

Chapter 1 USB Interface

Describes the functions and specifications of the USB interface used to control the AQ1100A, AQ1100B, and AQ1100D OLTS Multi Field Tester from a PC.

Chapter 2 Ethernet Interface (Option)

Describes the functions and specifications of the Ethernet interface.

Chapter 3 Before Programming

Describes the syntax used to transmit commands.

Chapter 4 Commands

Describes each command that is available.

Chapter 5 Condition Register / Output Queue and Error Queue

Describes the register and queues.

Appendix

Explains the support for AQ1100A, AQ1100B, and AQ1100D error cord.

ii IM AQ1100-17EN

Conventions Used in This Manual

Notations Used in the Procedural Explanations

On pages that describe the operating procedures in each chapter, the following notations are used to distinguish the procedure from their explanations.

Procedure

This subsection contains the operating procedure used to carry out the function described in the current section. The procedures are written with inexperienced users in mind; experienced users may not need to carry out all the steps.

Explanation

This subsection describes the setup parameters and the limitations on the procedures.

Note

Calls attention to information that is important for proper operation of the instrument.

Terms Used in Explanations of Procedures

Panel Keys and Soft Keys

Bold characters used in the procedural explanations indicate characters that are marked on the panel keys or the characters of the soft keys displayed on the screen menu.

Units

k: Denotes "1000." Example: 400km

K: Denotes "1024." Example: 459 KB (file data size)

IM AQ1100-17EN

Symbols Used in Syntax Descriptions Symbols which are used in the syntax descriptions in Chapter 5 are shown below.

These symbols are referred to as BNF notation (Backus-Naur Form).

For detailed information, see section 3.4, "Data."

Symbol	Description	Example	Example of Input
<>	Defined value	SET:M $<$ x $>$ $<$ x $>$ = 1,2,3	-> SET:M2
{}	One of the options in {} is selected.	LMTechnique {LSA TPA}	-> LMTechnique TPA
1	Exclusive OR		

iv IM AQ1100-17EN

Contents

	How t	to Use this Manual	ii
	Conve	entions Used in This Manual	iii
Chapter 1	USB	3 Interface	
	1.1	Names and Functions of Parts	1-1
	1.2	USB Interface Functions and Specifications	
	1.3	Connecting via the USB Interface	
	1.4	Setting the AQ1100A, AQ1100B, or AQ1100D (USB)	
Chapter 2	Ethe	ernet Interface (Option)	
•	2.1	Names and Functions of Parts	2-1
	2.2	Ethernet Interface Functions and Specifications	
	2.3	Connecting the Ethernet Interface	
	2.4	Setting the AQ1100A, AQ1100B, or AQ1100D (Network)	
Chapter 3	Befo	ore Programming	
•	3.1	Messages	3-1
	3.2	Commands	3-3
	3.3	Response	3-5
	3.4	Data	3-6
Chapter 4	Con	nmands	
•	4.1	List of Commands	4-1
	4.2	COMMunicate Group	4-4
	4.3	LIGHtsource Group	4-5
	4.4	MENU Group	4-6
	4.5	MISC Group	4-7
	4.6	NETWork Group	4-9
	4.7	PMETer Group	4-11
	4.8	PON Group	4-13
	4.9	PRINt Group	4-15
	4.10	SETup Group	4-16
	4.11	STATus Group	
	4.12	SYSTem Group	4-18
	4.13	VLS Group	
	4.14	Common Commands	4-20
Chapter 5	Con	dition Register / Output and Error Queue	
	5.1	Condition Register	5-1
	5.2	Output and Error Queue	5-2

Appendix

Index

1

2

3

4

J


App

Index


1

1.1 Names and Functions of Parts

Front Panel



Bottom



USB type B (mini B) connector Connector used to connect the AQ1100 to the controller (such as a PC) using a USB cable.

IM AQ1100-17EN 1-1

1.2 USB Interface Functions and Specifications

USB Interface Functions and Specifications

Reception Function

You can specify the same settings as those specified by front panel key operations. Receives output requests for measured data, setup data of the panel, and error codes.

Transmission Function

Outputs measured and computed data.

Outputs panel setup data and the status byte.

Outputs error codes that have occurred.

USB Interface Specifications

Electrical and mechanical specifications: Conforms to USB Rev.1.1

Connector: Type B (mini B) connector (receptacle)

Number of ports: 1

Power supply: Self-powered

Compatible PC systems: PC running Windows 2000, Windows XP, or Windows

Vista with a standard USB port (a separate device driver

is needed to connect to a PC).

Switching between Remote and Local Modes

When Switching from Local to Remote Mode

Sending a command when the instrument is in the local mode causes the instrument to switch to the remote mode.

- · All keys except the Local soft key are disabled.
- Settings entered in local mode are retained even when the AQ1100A, AQ1100B, or AQ1100D switches to remote mode.

When Switching from Remote to Local Mode

Pressing the Local soft key in remote mode puts the instrument in local mode.

- · Key operations are enabled.
- Settings entered in remote mode are retained even when the AQ1100A, AQ1100B, or AQ1100D switches to local mode.

Note.


The AQ1100A, AQ1100B, or AQ1100D cannot be remotely controlled via the USB interface while the storage function is in operation. Remote control via the Ethernet interface is also not possible.

1-2 IM AQ1100-17EN

1.3 Connecting via the USB Interface

Connection Procedure

- 1. Open the bottom cover of the left side.
- 2. Connect a USB cable to the type B (mini B) connector.



Precautions to Be Taken When Connecting the Cable

- Connect the USB cable by inserting the connector firmly into the USB connector.
- Do not connect or disconnect the USB cable after the power is turned ON until the AQ1100A, AQ1100B, or AQ1100D is ready for operation (approximately 20 s).


IM AQ1100-17EN 1-3

1.4 Setting the AQ1100A, AQ1100B, or AQ1100D (USB)

Procedure

Selecting the USB Interface Function

1. Press SETUP and then the System Setup soft key to display the following screen.



Releasing the Remote Control

1. Press the Local soft key that appears on the screen after communication starts.



Explanation

USB Interface

To control the AQ1100A, AQ1100B, or AQ1100D remotely using communication commands through the USB port, install YOKOGAWA'S TMC (Text and Measurement Class) driver into your PC. To obtain YOKOGAWA'S USB TMC driver, contact your nearest YOKOGAWA dealer or access the following USB driver page at our Web site and download it.

http://www.yokogawa.com/tm/tm-softdownload.htm


Note.

- You cannot change the display while the AQ1100A, AQ1100B, or AQ1100D is being remotely controlled.
- Only use the USB TMC driver (or software) provided by YOKOGAWA.


1-4 IM AQ1100-17EN

2.1 Names and Functions of Parts

Front Panel



Bottom



Connector used to connect the AQ1100 to the controller (such as a PC) using a ethernet cable.

IM AQ1100-17EN 2-1

2.2 Ethernet Interface Functions and Specifications

Ethernet Interface Features

Reception Feature

The AQ1100A, AQ1100B, or AQ1100D reception feature allows you to specify the same settings through an Ethernet connection that you can specify using the front panel keys.

The AQ1100A, AQ1100B, or AQ1100D can receive output requests for measured data, panel setting data, and error codes.

Transmission Feature

The AQ1100A, AQ1100B, or AQ1100D can transmit measured data.

The AQ1100A, AQ1100B, or AQ1100D can transmit panel setting data and the status byte.

The AQ1100A, AQ1100B, or AQ1100D can transmit error codes when errors occur.

Ethernet Interface Specifications

Electrical and mechanical specifications: Conforms to IEEE802.3 Transmission system: Ethernet (10BASE-T/100BASE-TX)

Data rate: 10 Mbps/100 Mbps Number of communication ports: 1

Port number: 10001/tcp

Communication protocol: VXI-11 Connector type: RJ45 connector

Switching between Remote and Local Modes When Switching from Local to Remote Mode

Sending a command when the instrument is in the local mode causes the instrument to switch to the remote mode.

- · All keys except the Local soft key are disabled.
- Settings entered in local mode are retained even when the AQ1100A, AQ1100B, or AQ1100D switches to remote mode.

When Switching from Remote to Local Mode

Pressing the Local soft key in remote mode puts the instrument in local mode.

- · Key operations are enabled.
- Settings entered in remote mode are retained even when the AQ1100A, AQ1100B, or AQ1100D to local mode.

Note_

The AQ1100A, AQ1100B, or AQ1100D cannot be remotely controlled via the USB interface while the storage function is in operation. Remote control via the Ethernet interface is also not possible.

FTP Function


The AQ1100A, AQ1100B, or AQ1100D has an FTP function. You can transfer the data stored in the AQ1100A, AQ1100B, and AQ1100D internal memory to the PC using FTP commands from the PC.

2-2 IM AQ1100-17EN

2.3 Connecting the Ethernet Interface

Connection Procedure

- 1. Open the bottom cover of the right side.
- Connect a UTP (Unshielded Twisted-Pair) cable or an STP (Shielded Twisted-Pair) cable that is connected to a hub, for example, to the 100BASE-TX port on the bottom of the AQ1100A, AQ1100B, or AQ1100D.



* UTP cable or STP cable (straight cable in either case)

Precautions to Be Taken When Connecting the Cable

- Be sure to use a straight cable via a hub for the connection between the AQ1100A, AQ1100B, or AQ1100D and the PC.
- Use a network cable that conforms to your network environment (such as the data rate).
- When using a UTP cable (straight cable), use a cable of category 5.

IM AQ1100-17EN 2-3


2.4 Setting the AQ1100A, AQ1100B, or AQ1100D (Network)

The settings for remotely controlling the AQ1100A, AQ1100B, or AQ1100D via the Ethernet interface are explained below.

Procedure

Selecting the Ethernet Interface Function

1. Press **SETUP** and then the **System Setup** soft key to display the following screen.



Releasing the Remote Control

1. Press the Local soft key that appears on the screen after communication starts.



2-4 IM AQ1100-17EN

Explanation

Setting the Ethernet Interface

You must set the following parameters to use the Ethernet interface function.

· Enabling or Disabling the Network Setup

After you have set the user name, password, timeout value, and TCP/IP parameters, select Valid and then restart the AQ1100A, AQ1100B, or AQ1100D to use the network connection.

- User Name
- Password

· Setting the Timeout Value

The connection to the network is automatically disconnected if there is no access to the AQ1100A, AQ1100B, or AQ1100D for the specified time.

Setting the TCP/IP

IP Address

Subnet Mask

Default Gateway

For details on how to configure the settings, see section 10.4, "Configuring Network Settings (Option)," in the *AQ1100A*, *AQ1100B*, *AQ1100D Multi Field Tester OLTS User's Manual*, IM AQ1100-01EN.

Note:

- You must restart the AQ1100A, AQ1100B, or AQ1100D if you change the Ethernet settings. Before you
 restart the AQ1100A, AQ1100B, or AQ1100D, the settings from before you changed the settings are used.
- The AQ1100A, AQ1100B, or AQ1100D cannot be remotely controlled via the ethernet interface while the USB storage function is in operation.

IM AQ1100-17EN 2-5

3.1 Messages

Messages


Messages are used to exchange information between the controller and the instrument. Messages that are sent from the controller to the instrument are called program messages and messages that are sent back from the instrument to the controller are called response messages.

If a program message contains a message unit that requests a response (a query), the instrument returns a response message upon receiving the program message. A single response message is always returned in response to a single program message.

Program Messages Program Message Unit

A program message consists of zero or more program message units; each unit corresponds to one command. The instrument executes the received commands in order.

Each program message unit is separated by a semicolon (;).



<PMT>

PMT is a program message terminator. The following three types are available.

- NL (New Line)
 Same as LF (Line Feed). ASCII code"0AH" is used.
- END message defined in IEEE488.1. (EOI signal)
 (The data byte sent with an END message will be
- the final item of the program message unit.)NL^ENDNL with an END message added (NL is not included)


Program Header

in the program message unit.)

A program header is used to indicate the command type. For details, see section 3.2, "Commands."


Program Data

If certain conditions are required in executing a command, program data is added. A space (ASCII code "20H") separates the program data from the header. If there are multiple sets of program data, they are separated by commas (,). For details, see section 3.4, "Data."



Response Message Units

A response message consists of one or more response message units: each response message unit corresponds to one response. Response message units are delimited by a ";" (semicolon).



<RMT>


RMT stands for "response message terminator." The response message terminator is NL^EOM.

Response Header

A response header sometimes precedes the response data. A space separates the data from the header. For details, see section 3.3, "Response."

Response Data

Response data contains the content of the response. If there are multiple sets of response data, they are separated by commas (,). For details, see section 3.4, "Data."



If there are multiple queries in a program message, responses are returned in the same order that the queries were received in. This instrument returns a single response message unit to most queries, but there are queries that this instrument returns multiple units to. The first response message unit always corresponds to the first query, but the nth response unit may not necessarily correspond to the nth query. If you want to make sure that every response is retrieved, divide the program messages into individual messages.

IM AQ1100-17EN 3-1

3.1 Messages

Note-

- It is always possible to send a program message if the previous message which was sent did not contain any queries.
- If the previous message contained a query, it is not possible to send another program message until a response message has been received. An error will occur if a program message is sent before a response message has been received in its entirety. A response message which has not been receivedwill be discarded.
- If an attempt is made by the controller to receive
 a response message, even if there it no response
 message, an error will occur. An error will also occur if
 the controller makes an attempt to receive a response
 message before transmission of a program message has
 been completed.
- If a program message of more than one unit is sent and some of the units are incomplete, this instrument receives program message units which the instrument thinks complete and attempts to execute them. However, these attempts may not always be successful and a response may not always be returned, even if the program message contains queries.

3-2 IM AQ1100-17EN

3.2 Commands

Command

There are three types of commands (program headers) that a controller may send to the DLM2000. The commands differ in their program header formats.

Common Command Header

Commands that are defined in IEEE 488.2-1987 are called common commands. Be sure to include an asterisk (*) at the beginning of a common command.

Common command example *CLS

Compound Header

Other commands that are specific to this instrument are classified and arranged in a hierarchy according to their functions. Be sure to use a colon to specify a lower hierarchical level.

Compound header example : PMETer:LINK:STATe

When Concatenating Commands Command Groups

A command group is a group of commands that have common compound headers arranged in a hierarchy. A command group may contain sub-groups.

Example

Commands relating to acquisition settings

:PMETer:DREF

:PMETer:LINK:STATe

:PMETer:MAXMin:STATe

:PMETer:MODulation

:PMETer:OFFSet

:PMETer:REFerence

:PMETer:WAVelength:DETail

When Concatenating Commands of the Same Group

This instrument stores the hierarchical level of the command that is currently being executed and processes the next command on the assumption that it belongs to the same level. Therefore, the common header section can be omitted for commands that belong to the same group.

Example

:PMETer:MODulation MOD CW;UNIT DB<PMT>

When Concatenating Commands of Different Groups

If the subsequent command does not belong to the same group, place a colon in front of the header (cannot be omitted).

Example

:PMETer:MODulation MOD_ CW;:MENU:FUNCtion TOP<PMT>

When Concatenating Common Commands

Common commands that are defined in the IEEE 488.2-1987 are independent of hierarchy. There is no need to use a colon.

Example

:PMETer:MODulation MOD_CW;*CLS;UNIT DB<PMT>

When Separating Commands with <PMT>

If a terminator is used to separate two commands, each command is a separate message. Therefore, the common header must be typed in for each commandeven when commands of the same command groupare being concatenated.

Example

:PMETer:MODulation MOD_CW<PMT>:PMETer
UNIT DB<PMT>

Upper-level Query

An upper-level query is a query that is made by appending a question mark to the highest level command of a group. The controller can receive all of the settings in a group collectively by executing an upper-level query. Some upper-level queries of a group, which may be comprised of more than three hierarchical levels, can cause this instrument to transmit all the lower level settings.

Example

```
:NETWork:CONTrol?<PMT> ->
:NETW:CONT:PASS "ABC";TIM 30;USER
"anonyumous"
```

Note-

- The response to an upper-level query can be sent back to this instrument as a program message. This enables the settings that were present when the upper-level query was made to be reproduced later on.
- Some upper-level queries do not return setup data that is not currently in use. Exercise caution because not all of a group's information is necessarily returned in a response.

IM AQ1100-17EN 3-3

Header Interpretation Rules

This instrument interprets the header that it receives according to the rules below.

Example

"DRANge" can be written as "drange" or "Drange."

• The lower-case characters can be omitted.

Example

"DRANGE" can be written as "DRANG" or "DRAN."

 The question mark at the end of a header indicates that it is a query. You cannot omit the question mark.
 Example

The shortest abbreviation for "DRANge?" is "DRAN?."

• If the <x> (value) at the end of a mnemonic is omitted, it is interpreted as a 1.

Example

If you write "M" for "M<x>, " "M1." is specified.

Note

A mnemonic is a character string made up of alphanumeric characters.)

3-4 IM AQ1100-17EN

3.3 Response

Form

When the controller sends a query with a question mark, this instrument returns a response message to the query.

Response Consisting of a Header and Data

Responses that can be used as program messages without any changes are returned with command headers attached.

Example

```
:PMETer:MODulation?<PMT>
-> :PMETer:MODulation MOD 270HZ<RMT>
```

If You Want this instrument to Return Responses without Headers

You can configure this instrument so that even responses that have both headers and data are returned without headers. Use the COMMunicate:HEADer command for this purpose.

Abbreviated Form

This instrument normally returns response headers with the lower-case section removed. You can configure this instrument so that full headers are returned. Use the COMMunicate:VERBose command for this purpose.

IM AQ1100-17EN 3-5

3.4 Data

Data contains conditions and values that are written after the header. A space separates the data from the header. Data is grouped as follows:

Data	Description			
<decimal></decimal>	A value expressed in decimal notation			
	(Example: Western calendar year			
	->MISC:DATE:YEAR 2009)			
<distance><time></time></distance>	A physical value			
<wavelength><loss></loss></wavelength>	(Example: Timeout value ->NETWork:			
	CONTrol:TIMeout 30))			
<character data=""></character>	Predefined character string (mnemonic).			
	Select from the available strings in brace			
	(Example: Select the function mode			
	->MENU: FUNCtion {TOP LSPM LOSStest			
	PONPm MLOSstest IPTest })			
<boolean></boolean>	Indicates ON and OFF. Specify ON or OFF.			
	(Example: Turn on the DHCP ->NETWork:			
	DHCP ON))			
<string data=""></string>	User-defined string			
	(Example: Set the Network password			
	->NETWork:CONTrol:PASSword "ABC")			

<Decimal>

<Decimal> indicates a value expressed as a decimal number, as shown in the table below. Decimal values are written in the NR form as specified in ANSI X3.42-1975.

Symbol	Description	Example		
<nr1></nr1>	Integer	125	-1	+1000
<nr2></nr2>	Fixed point number	125.0	90	+001.
<nr3></nr3>	Floating point number	125.0E+0	-9E-1	+.1E4
<nrf></nrf>	Any of the forms <nr1></nr1>	to <nr3> is</nr3>	allowed.	

- This instrument can receive decimal values that are sent from the controller in any form, from <NR1> to <NR3>. This is expressed as <NRf>.
- This instrument returns a response to the controller in one of the forms from <NR1> to <NR3> depending on the query. The same form is used regardless of the size of the value.
- For the <NR3> form, the plus sign after the "E" can be omitted. You cannot omit the minus sign.
- If a value outside the setting range is entered, the value is adjusted to the closest value within the range.
- If a value has more significant digits than are available, the value will be rounded.

<Distance>, <Time>, <Wavelength>, and <Loss>

<Distance>, <Time>, <Wavelength>, and <Loss> indicate decimal values that have physical significance. A <Multiplier> or <Unit> can be attached to the <NRf> form that was described earlier. The following types of expressions are possible.

Form	Example	
<nrf><multiplier><unit></unit></multiplier></nrf>	0.85UM	
<nrf><unit></unit></nrf>	500m	
<nrf><multiplier></multiplier></nrf>	5M	
<nrf></nrf>	5E -3	

<Multiplier>

<Multipliers> that you can use are indicated in the following table.

Symbol	Word	Description	
EX	Exa	10 ¹⁸	
PE	Peta	10 ¹⁵	
T	Tera	10 ¹²	
G	Giga	10 ⁹	
MA	Mega	10 ⁶	
K	Kilo	10 ³	
M	Milli	10 ⁻³	
U	Micro	10 ⁻⁶	
N	Nano	10 ⁻⁹	
P	Pico	10 ⁻¹²	
F	Femto	10 ⁻¹⁵	
Α	Atto	10 ⁻¹⁸	

<Unit>

<Units> that you can use are indicated in the following table.

Symbol	Word	Description	
M	Meter	Distance	
S	Second	Time	
dB	Decibel	Level	
UM	Micro meter	Wavelength	

- <Multiplier> and <Unit> are not case sensitive.
- "U" is used to indicate micro ("µ").
- "MA" is used for Mega to distinguish it from Milli.
- If both <Multiplier> and <Unit> are omitted, the default unit is used.

3-6 IM AQ1100-17EN

<Character Data>

<Character data> is a predefined character string (mnemonics). It is mainly used to indicate that an option listed as a character string in braces must be selected and entered. The data interpretation rules are the same as those described in "Header Interpretation Rules" on page 3-4.

Form	Example
{SIMPLE DETAIL WIZARD MULTI}	DETAIL

- As with the header, the COMMunicate: VERBose command can be used to select whether to return the response in the full form or in the abbreviated form.
- The COMMunicate: HEADer setting does not affect <character data>.

<Boolean>

<Boolean> is data that indicates ON or OFF. The following types of expressions are possible.

Form Exa		le		
{ON OFF <nrf>}</nrf>	ON	OFF	1	0

- When <Boolean> is expressed in the <NRf> form,
 "OFF" is selected if the rounded integer value is 0,
 and ON is selected for all other cases.
- A response message is always returned with a 1 if the value is ON and with a 0 if the value is OFF.

<String Data>

<String data> is not a predefined character string like <character data>. It can be any character string. The character string must be enclosed in single quotation marks (') or double quotation marks (").

Form			Examp	le
<character< td=""><td>string</td><td>data></td><td>'ABC'</td><td>"IEEE488.2-1987"</td></character<>	string	data>	'ABC'	"IEEE488.2-1987"

- If a character string contains a double quotation mark ("), the double quotation mark is expressed as two consecutive quotation marks (""). This rule also applies to single quotation marks.
- A response message is always enclosed in double quotation marks (").
- <String data> is any character string. Therefore, this
 instrument assumes that the remaining program
 message units are part of the character string
 if no single (') or double quotation mark (") is
 encountered. As a result, no error is detected if a
 quotation mark is omitted.

IM AQ1100-17EN 3-7

List of Commands

Command	Function	Page
COMMunicate Group		
:COMMunicate?	Queries all communication settings.	4-4
:COMMunicate:HEADer	Sets or queries whether or not a header is added to the response to a query. (Example with header: PMETer:REFerence 5.00. Example without header: 5.00.)	4-4
:COMMunicate:VERBose	Sets or queries whether the response to a query is returned fully spelled out (example: PMETer:REFerence 5.00) or using abbreviation (example: PMET: REF 5.00).	4-4
LIGHtsource Group		
:LIGHtsource:ABORt	Turns the measurement light off.	4-5
:LIGHtsource:EXECute	Turns the measurement light on.	4-5
:LIGHtsource:MODulation	Sets or queries the light source modulation frequency.	4-5
:LIGHtsource:WAVelength	Sets or queries the light source wavelength.	4-5
MENU Group		
:MENU:ERRor:CLEar	Clears the error dialog box.	4-6
:MENU:FUNCtion	Sets or gueries the function mode.	4-6
	4	
MISC Group		
:MISC:ALARmsound	Sets or queries the alarm sound.	4-7
:MISC:BRIGhtness:AC	Sets or queries the LCD brightness when the AC adapter is connected.	4-7
:MISC:BRIGhtness:BATTery	Sets or queries the LCD brightness when this instrument is running on battery power.	4-7
:MISC:BACKlightoff	Sets or queries the backlight off setting when this instrument is running on	4-7
:MISC:DATE:DAY	battery power. Sets or queries the day.	4-7
:MISC:DATE:GET?	Queries the date and time.	4-7
:MISC:DATE:HOUR		4-7
:MISC:DATE:MINute	Sets or queries the hour.	
	Sets or queries the minute.	4-7
:MISC:DATE:MODE	Sets or queries the date display type.	4-7 4-7
:MISC:DATE:MONTh	Sets or queries the month.	4-7
:MISC:DATE:SECond	Sets or queries the second.	
:MISC:DATE:SET :MISC:DATE:YEAR	Applies the date and time change.	4-8
	Sets or queries the year.	4-8
:MISC:LANGuage	Sets or queries the language.	4-8
:MISC:POWersave:AC :MISC:POWersave:BATTery	Sets or queries the power-save setting when the AC adapter is connected. Sets or queries the power-save setting when this instrument is running on	4-8 4-8
	battery power.	
NETWork Group		
:NETWork:CONTrol:PASSword	Sets or queries the password.	4-9
:NETWork:CONTrol:TIMeout	Sets or queries the timeout value.	4-9
:NETWork:CONTrol:USERname	Sets or queries the user name.	4-9
:NETWork:DHCP	Sets or queries the DHCP on/off state.	4-9
:NETWork:GATeway	Sets or queries the gateway.	4-9
:NETWork:IPADdress	Sets or queries the IP address.	4-9
:NETWork:NETMask	Sets or queries the subnet mask.	4-10
:NETWork:STATe	Sets or queries the Ethernet on/off state.	4-10

4-1 IM AQ1100-17EN

4.1 A List of Commands

Command	Function	Page
PMETer Group		
: PMETer: AVERage: TIMes	Sets or queries the power meter average count.	4-11
:PMETer:DREF	Executes Dref on the power meter.	4-11
:PMETer:LINK:STATe	Sets or queries the light source power meter setting interlock.	4-11
:PMETer:MAXMin:STATe	Sets or queries the MAX and MIN display on/off state.	4-11
:PMETer:MAXMin:MAX?	Sets or queries the maximum value.	4-11
:PMETer:MAXMin:MIN?	Sets or queries the minimum value.	4-11
:PMETer:MEASurement:DATA?	Queries the power meter's measured results.	4-11
:PMETer:MODulation	Sets or queries the power meter s measured results.	4-11
:PMETer:OFFSet	Sets or queries the power meter infodulation. Sets or queries the power meter offset.	4-11
:PMETer:REFerence	Sets or queries the power meter offset. Sets or queries the power meter reference value.	4-11
:PMETer:THReshold:LOWer	Sets or queries the power meter lower threshold value.	4-11
:PMETer:THReshold:UPPer	Sets or queries the power meter lower threshold value. Sets or queries the power meter upper threshold value.	4-12
:PMETer:UNIT	Sets or queries the power meter display unit.	4-12
:PMETer:WAVelength:DETail	Sets or queries the power meter display unit. Sets or queries the wavelength when the wavelength mode is set to Detail.	4-12
:PMETer:ZERoset	Executes zero set on the power meter.	4-12
.FMEIGI.ZEROSEC	Executes Zero set on the power meter.	4-12
PON Group		
:PON:AVERage:TIMes	Sets or queries the PON power meter average count.	4-13
:PON:DIRection	Sets or queries the PON power meter wavelength.	4-13
:PON:M1310:MEASurement:DATA?	Queries the measured results of the 1310 nm PON power meter.	4-13
:PON:M1310:OFFSet	Sets or queries the 1310 nm PON power meter offset.	4-13
:PON:M1310:THReshold:JUDGe?	Queries the threshold judgment results of the 1310 nm PON power meter.	4-13
:PON:M1310:THReshold:LOWer	Sets or queries the lower threshold value of the 1310 nm PON power meter.	4-13
:PON:M1310:THReshold:UPPer	Sets or queries the upper threshold value of the 1310 nm PON power meter.	4-13
:PON:M1490:MEASurement:DATA?	Queries the measured results of the 1490 nm PON power meter.	4-13
:PON:M1490:OFFSet	Sets or queries the 1490 nm PON power meter offset.	4-13
:PON:M1490:THReshold:JUDGe?	Queries the threshold judgment results of the 1490 nm PON power meter.	4-13
:PON:M1490:THReshold:LOWer	Sets or queries the lower threshold value of the 1490 nm PON power meter.	4-13
:PON:M1490:THReshold:UPPer	Sets or queries the upper threshold value of the 1490 nm PON power meter.	4-14
:PON:M1550:MEASurement:DATA?	Queries the measured results of the 1550 nm PON power meter.	4-14
:PON:M1550:OFFSet	Sets or queries the 1550 nm PON power meter offset.	4-14
:PON:M1550:THReshold:JUDGe?	Queries the threshold judgment results of the 1550 nm PON power meter.	4-14
:PON:M1550:THReshold:LOWer	Sets or queries the lower threshold value of the 1550 nm PON power meter.	4-14
:PON:M1550:THReshold:UPPer	Sets or queries the upper threshold value of the 1550 nm PON power meter.	4-14
:PON:UNIT	Sets or queries the PON power meter display unit.	4-14
:PON:ZERoset	Executes zero set on the PON power meter.	4-14
PRINt Group	Cate as suspined the print calcus	4.45
:PRINt:COLor	Sets or queries the print colors.	4-15
:PRINt:EXECute	Executes printing.	4-15
:PRINt:MAKer	Sets or queries the printer manufacturer.	4-15
SETup Group		
:SETup:INITialize	Returns all settings to their factory defaults.	4-16
STATus Group:	Ouering all the cettings for the communication status feature	1 17
	Queries all the settings for the communication status feature.	4-17
:STATus:CONDition?	Queries the contents of the condition register.	4-17
:STATus:ERRor?	Queries the error code and message information (top of the error queue).	4-17
:STATus:QENable	Sets or queries whether or not messages other than errors will be stored to the error queue (on/off).	e 4-1/
:STATus:QMESsage	Sets or queries whether or not message information will be attached to the response to the STATus:ERRor? query (on/off).	4-17
evetam Graup		
SYSTem Group :SYSTem:REBoot	Restarts this instrument.	4-18
:SYSTem:REBOOT :SYSTem:SHUTdown	Shuts down this instrument.	4-18
		4-18

4-2 IM AQ1100-17EN

Command	Function	Page
VLS Group		
:VLS:ABORt	Turns the visible light source off.	4-19
:VLS:EXECute	Turns the visible light source on.	4-19
Common Commands		
*CLS (Clear Status)	Clears all event status registers that are displayed in the status byte register summary.	4-20
*ESE (Standard Event Status Enable)	Sets or queries the standard event enable register.	4-20
*ESR? (Standard Event Status Register)	Queries and clears the standard event status register.	4-20
*IDN? (Identification)	Queries the instrument type and firmware version.	4-20
*OPT? (Option)	Queries the option information.	4-20
*RST (Reset)	Returns all the settings except the communication settings to their factory default values.	4-20
*SRE (Service Request Enable)	Sets or queries the service request enable register.	4-21
*STB? (Read Status Byte)	Queries the current status byte register value.	4-21
*TST? (Self Test)	Executes a self-test.	4-21

IM AQ1100-17EN 4-3

4.2 COMMunicate Group

The commands in this group deal with communications. There are no front panel keys that correspond to the commands in this group.

:COMMunicate?

Function Queries all communication settings.

Syntax : COMMunicate?

Example : COMMUNICATE: -> : COMMUNICATE: HEADER

1; VERBOSE 0

:COMMunicate:HEADer

Function Sets or queries whether or not a header is added

to the response to a query. (Example with header: PMETer:REFerence 5.00. Example without header:

5.00.)

Syntax :COMMunicate:HEADer {<Boolean>}

:COMMunicate:HEADer?

Example : COMMUNICATE: HEADER ON

:COMMUNICATE:HEADER? ->:COMMUNICATE:

HEADER 1

:COMMunicate:VERBose

Function Sets or gueries whether the response to a guery

is returned fully spelled out (example: PMETer: REFerence 5.00) or using abbreviation (example:

PMET:REF 5.00).

Syntax :COMMunicate:VERBose {<Boolean>}

:COMMunicate:VERBose?

Example : COMMUNICATE: VERBOSE ON

:COMMUNICATE:VERBOSE?
->:COMMUNICATE:VERBOSE 0

4-4 IM AQ1100-17EN

4.3 LIGHtsource Group

The commands in this group deal with the light source. You can perform the same operations and make the same settings and queries that you can by using the front panel.

:LIGHtsource:ABORt

Function Turns the measurement light off.

Syntax :LIGHtsource:ABORt
Example :LIGHTSOURCE:ABORT

:LIGHtsource:EXECute

Function Turns the measurement light on.

Syntax : LIGHtsource:EXECute

Example :LIGHTSOURCE:EXECUTE

Description Measurement light and visible light cannot be on at

the same time.

:LIGHtsource:MODulation

Function Sets or queries the light source modulation

frequency.

Syntax :LIGHtsource:MODulation {MOD_CW|

MOD_270HZ|MOD_1KHZ|MODE_2KHZ}
:LIGHtsource:MODulation?

Example :LIGHTSOURCE:MODULATION MOD_CW

:LIGHTSOURCE:MODULATION?

-> :LIGHTSOURCE:MODULATION MOD CW

Description When :LIGHtsource:WAVelength is set to 0.850 um

or 1.300 um, the modulation frequency can only be

set to CW or 270 Hz.

$: \verb+LIGHtsource: WAVelength+$

Function Sets or queries the light source wavelength.

Syntax :LIGHtsource:WAVelength {<NRf>}

:LIGHtsource:WAVelength? <NRf> = 0.850um to 1.650um

(850E-9 to 1650E-9)

Example :LIGHTSOURCE:WAVELENGTH 0.85um

:LIGHTSOURCE:WAVELENGTH 1650E-9 :LIGHTSOURCE:WAVELENGTH 1.650E-6

:LIGHTSOURCE:WAVELENGTH?

-> :LIGHTSOURCE:WAVELENGTH 1550E-09

Description The wavelengths that can be specified vary

depending on the model.

IM AQ1100-17EN 4-5

4.4 MENU Group

The commands in this group are used to set the function or marker mode or query the settings.

:MENU:ERRor:CLEar

Function Clears the error dialog box.

Syntax :MENU:ERROR:CLEAR

Example :MENU:ERROR:CLEAR

:MENU:FUNCtion

Function Sets or queries the function mode.

Syntax :MENU:FUNCtion {TOP|LSPM|LOSStest|

PONPm|MLOSstest|IPTest}

:MENU:FUNCtion?

Example : MENU: FUNCTION TOP

:MENU:FUNCTION? -> :MENU:FUNCTION LSPM

Description Top menu: TOP

Light source power meter: LSPM
Auto loss test: LOSStest
PON power meter: PONPm
Multi-core loss test: MLOSstest
IPtest: IPTest

- 1 Can only be selected on products whose power meter suffix code is SPM or HPM.
- 2 Can only be selected on products whose power meter suffix code is PON.
- 3 Can only be selected on products with the LAN option.

4-6 IM AQ1100-17EN

4.5 MISC Group

The commands in this group deal with the date, language, and power management. You can make the same settings and queries that you can by using the front panel.

:MISC:ALARmsound

Function Sets or queries the alarm sound.

Syntax :MISC:ALARmsound {<Boolean>}

:MISC:ALARmsound?

Example :MISC:ALARMSOUND OFF

:MISC:ALARMSOUND?
-> :MISC:ALARMSOUND 1

:MISC:BRIGhtness:AC

Function Sets or queries the LCD brightness when the AC

adapter is connected.

Syntax :MISC:BRIGhtness:AC {BRIGHT|NORMAL

|DARK}

:MISC:BRIGhtness:AC?

Example :MISC:BRIGHTNESS:AC NORMAL

:MISC:BRIGHTNESS:AC?

-> :MISC:BRIGHTNESS:AC NORMAL

Description Bright: BRIGHT

Normal: NORMAL Power save: DARK

:MISC:BRIGhtness:BATTery

Function Sets or queries the LCD brightness when this

instrument is running on battery power.

Syntax :MISC:BRIGhtness:BATTery {BRIGHT|

NORMAL | DARK }

:MISC:BRIGhtness:BATTery?

Example :MISC:BRIGHTNESS:BATTERY NORMAL

:MISC:BRIGHTNESS:BATTERY?

-> :MISC:BRIGHTNESS:BATTERY NORMAL

Description The parameters are the same as those for :MISC:

BRIGhtness:AC.

:MISC:BACKlightoff

Function Sets or queries the backlight off setting when this

instrument is running on battery power.

Syntax :MISC:BACKlightoff {<Boolean>}

Example :MISC:BACKLIGHTOFF ON

:MISC:BACKLIGHTOFF?
-> :MISC:BACKLIGHTOFF 1

:MISC:DATE:DAY

Function Sets or queries the day.

Syntax :MISC:DATE:DAY {<NRf>}

 $\langle NRf \rangle = 1 \text{ to } 31 \text{ (in steps of 1)}$

:MISC:DATE:DAY?

Example :MISC:DATE:DAY 1

:MISC:DATE:DAY? -> :MISC:DATE:DAY 1

Description This setting takes effect when :MISC:DATE:SET is

executed.

:MISC:DATE:GET?

Function Queries the date and time.

Syntax :MISC:DATE:GET?

Example :MISC:DATE:GET?

-> :MISC:DATE:GET 2009/01/31 23:59:59

:MISC:DATE:HOUR

Function Sets or queries the hour.

Syntax :MISC:DATE:HOUR {<NRf>}

:MISC:DATE:HOUR?

<NRf> = 0 to 23 (in steps of 1)

Example :MISC:DATE:HOUR 17

:MISC:DATE:HOUR?
-> :MISC:DATE:HOUR 12

Description This setting takes effect when :MISC:DATE:SET is

executed.

:MISC:DATE:MINute

Function Sets or queries the minute.

Syntax :MISC:DATE:MINUTE {<NRf>}

<NRf> = 0 to 59 (in steps of 1)
:MISC:DATE:MINute?

Example :MISC:DATE:MINUTE 5
:MISC:DATE:MINUTE?

-> :MISC:DATE:MINUTE 59

Description This setting takes effect when :MISC:DATE:SET is

executed

:MISC:DATE:MODE

Function Sets or queries the date display type.

Syntax :MISC:DATE:MODE {TYPE1|TYPE2|TYPE3}

:MISC:DATE:MODE?

Example :MISC:DATE:MODE TYPE1

:MISC:DATE:MODE?

-> :MISC:DATE:MODE TYPE2

Description Date display types

2009/08/29 12:16 TYPE1 08/29/2006 12:16 TYPE2 2009/AUG/29 12:16 TYPE3

:MISC:DATE:MONTh

Function Sets or queries the month.

Syntax :MISC:DATE:MONTh {<NRf>}

< NRf > = 1 to 12

:MISC:DATE:MONTh?

Example :MISC:DATE:MONTh 8

:MISC:DATE:MONTH? -> MISC:DATE:MONTH 8

Description This setting takes effect when :MISC:DATE:SET is

executed.

IM AQ1100-17EN 4-7

4.5 MISC Group

:MISC:DATE:SECond

Function Sets or queries the second.

Syntax :MISC:DATE:SECond {<NRf>}

 $\langle NRf \rangle = 0$ to 59 (in steps of 1)

Example :MISC:DATE:SECOND 0

:MISC:DATE:SECOND?
-> :MISC:DATE:SECOND 0

Description This setting takes effect when :MISC:DATE:SET is

executed.

:MISC:DATE:SET

Function Applies the date and time change.

Syntax :MISC:DATE:SET Example :MISC:DATE:SET

:MISC:DATE:YEAR

Function Sets or queries the year.

Syntax :MISC:DATE:YEAR {<NRf>}

<NRf> = 2009 to 2035 (in steps of 1)

:MISC:DATE:YEAR?

Example :MISC:DATE:YEAR 2009

:MISC:DATE:YEAR? -> :MISC:DATE:YEAR

2009

Description This setting takes effect when :MISC:DATE:SET is

executed.

:MISC:LANGuage

Function Sets or queries the language.

Syntax :MISC:LANGuage {JAPANESE|ENGLISH}

:MISC:LANGuage?

Example :MISC:LANGUAGE ENGLISH

:MISC:LANGUAGE? -> :MISC:LANGUAGE

ENGLISH

:MISC:POWersave:AC

Function Sets or queries the power-save setting when the AC

adapter is connected.

Syntax :MISC:POWersave:AC {OFF|A1MIN|A5MIN|A10

MIN|A30MIN}

:MISC:POWersave:AC?

Example :MISC:POWERSAVE:AC A1MIN

:MISC:POWERSAVE:AC? -> :MISC:POWERSAVE:

AC OFF

Description Disable: OFF

Power save after 1 minute: A1MIN
Power save after 5 minutes: A5MIN
Power save after 10 minutes: A10MIN
Power save after 30 minutes: A30MIN

:MISC:POWersave:BATTery

Function Sets or queries the power-save setting when this

instrument is running on battery power.

Syntax :MISC:POWersave:BATTery {OFF|A1MIN|

A5MIN|A10MIN|A30MIN}
:MISC:POWersave:BATTery?

Example :MISC:POWERSAVE:BATTERY A1MIN

:MISC:POWERSAVE:BATTERY? -> :MISC:

POWERSAVE: BATTERY OFF

Description The parameters are the same as those for :MISC:

POWersave:AC.

4-8 IM AQ1100-17EN

4.6 NETWork Group

The commands in this group can only be used on models with the /LAN option.

:NETWork:CONTrol:PASSword

Function Sets or queries the password.

Syntax : NETWork: CONTrol: PASSword <character string>

Example : NETWORK: CONTROL1: PASSWORD "ABC"

:NETWORK:CONTROL1:PASSWORD?

-> :NETWORK:CONTROL1:PASSWORD "ABC"

Description You cannot use this command if NETWork:STATe is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

You do not have to set the password when the user

name is "anonymous."

:NETWork:CONTrol:TIMeout

Function Sets or queries the timeout value.

Syntax :NETWork:CONTrol:TIMeout

{<NRf>|INFinite}

:NETWork:CONTrol:TIMeout?

<NRf>: 1 to 3600

Example : NETWORK: CONTROL: TIMEOUT 30

:NETWORK:CONTROL:TIMEOUT?

-> :NETWORK:CONTROL:TIMEOUT 30

Description The unit is seconds.

You cannot use this command if NETWork:STATe is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

:NETWork:CONTrol:USERname

Function Sets or queries the user name.

Syntax :NETWork:CONTrol:USERname <character string>
Example :NETWORK:CONTROL:USERNAME "anonymous"

Example :NETWORK:CONTROL:USERNAME "anonymo

:NETWORK:CONTROL:USERNAME?
-> :NETWORK:CONTROL:USERNAME

"anonyumous"

Description You cannot use this command if NETWork:STATe is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

:NETWork:DHCP

Function Sets or queries the DHCP on/off state.

Syntax :NETWork:DHCP <Boolean>

:NETWork:DHCP?

Example : NETWORK: DHCP ON

:NETWORK:DHCP? -> :NETWORK:DHCP 1

Description Invalid: OFF or 0

Valid: ON or 1

You cannot use this command if NETWork:STATe is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

:NETWork:GATeway

Function Sets or queries the gateway.

Syntax : NETWork: GATeway < character string>

:NETWork:GATeway?

Example :NETWORK:GATEWAY "255.255.25.0"

:NETWORK:GATEWAY? -> :NETWORK:

GATEWAY "255.255.255.0"

Description You cannot use this command if NETWork:STATe is

set to OFF.

You cannot use this command if NETWork:DHCP is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

:NETWork:IPADdress

Function Sets or queries the IP address.

Syntax : NETWork: IPADdress <character string>

:NETWork:IPADdress?

Example :NETWORK:IPADDRESS "192.168.0.1"

:NETWORK:IPADDRESS? -> :NETWORK:

IPADDRESS "192.168.0.1"

Description You cannot use this command if NETWork:STATe is

set to OFF.

You cannot use this command if NETWork: DHCP is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

IM AQ1100-17EN 4-9

4.6 NETWork Group

:NETWork:NETMask

Function Sets or queries the subnet mask.

Syntax : NETWork: NETMask < character string>

:NETWork:NETMask?

Example :NETWORK:NETMASK "255.255.255.0"

:NETWORK:NETMASK? -> :NETWORK:

NETMASK "255.255.255.0"

Description You cannot use this command if NETWork:STATe is

set to OFF.

You cannot use this command if NETWork:DHCP is

set to OFF.

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

:NETWork:STATe

Function Sets or queries the Ethernet on/off state.

Syntax :NETWork:STATe <Boolean>

:NETWork:STATe?

Example : NETWORK: STATE ON

:NETWORK:STATE? -> :NETWORK:STATE 1

Description Invalid: OFF or 0

Valid: ON or 1

The setting specified by this command takes effect when this instrument is restarted. You can restart this

instrument by using :SYSTem:REBoot.

4-10 IM AQ1100-17EN

4.7 PMETer Group

The commands in this group deal with the power meter. You can make the same settings and queries that you can by using the front panel.

:PMETer:AVERage:TIMes

Function Sets or queries the power meter average count.

Syntax :PMETer:AVERage:TIMes <T1|T10|T50|T100>

:PMETer:AVERage:TIMes?

Example : PMETER: AVERAGE: TIMES T1

:PMETER:AVERAGE:TIMES? -> :PMETER:

AVERAGE: TIMES T1

Description T1: 1

T10: 10 T50: 50 T100: 100

:PMETer:DREF

Function Executes Dref on the power meter.

Syntax : PMETer:DREF
Example : PMETer:DREF

:PMETer:LINK:STATe

Function Sets or queries the light source power meter setting

interlock.

Syntax :PMETer:LINK:STATe {<Boolean>}

Example : PMETER:LINK:STATE ON

:PMETER:LINK:STATE?
-> :PMETER:LINK:STATE 1

:PMETer:MAXMin:STATe

Function Sets or queries the MAX and MIN display on/off

state.

Syntax :PMETer:MAXMin:STATe {<Boolean>}

Example : PMETER: MAXMIN: STATE ON

:PMETER:MAXMIN:STATE?
-> :PMETER:MAXMIN:STATE 1

:PMETer:MAXMin:MAX?

Function Sets or queries the maximum value.

Syntax : PMETer: MAXMin: MAX?

Example :PMETER:MAXMIN:MAX? -> :PMETER:MAXMIN:

MAX? 5.00

Description You can only make this query when :PMETer:

MAXMin:STATe is set to ON.

:PMETer:MAXMin:MIN?

Function Sets or gueries the minimum value.

Syntax : PMETer: MAXMin: MIN?

Example : PMETER:MAXMIN:MIN? -> : PMETER:MAXMIN:

MIN? -5.00

Description You can only make this query when :PMETer:

MAXMin:STATe is set to ON.

: PMETer: MEASurement: DATA?

Function Queries the power meter's measured results.

Syntax : PMETer:MEASurement:DATA?
Example : PMETER:MEASUREMENT:DATA?

-> :PMETER:MEASUREMENT:DATA 26.56

:PMETer:MODulation

Function Sets or queries the power meter modulation.

Syntax :PMETer:MODulation {MOD 270HZ | MOD CW

|MOD 1KHZ|MOD 2KHZ}

Example : PMETER: MODULATION MOD_270HZ

: PMETER: MODULATION?

-> :PMETER:MODULATION MOD 270HZ

Description You cannot use this command on products whose

power meter suffix code is "PPM".

:PMETer:OFFSet

Function Sets or queries the power meter offset.

Syntax : PMETer:OFFSet {<NRf>}

:PMETer:OFFSet?

<NRf> = -9.900 to 9.900 (in steps of 0.001)

Example :PMETER:OFFSET -5.000

:PMETER:OFFSET?

-> :PMETER:OFFSET -3.000

:PMETer:REFerence

Function Sets or queries the power meter reference value.

Syntax : PMETer:REFerence {<NRf>}

:PMETer:REFerence?

<NRf> = -70.00 to 5.00 (in steps of 0.001) [dBm]

Example : PMETER: REFERENCE 0.00

:PMETER:REFERENCE?

-> :PMETER:REFERENCE 0.00

:PMETer:THReshold:LOWer

Function Sets or queries the power meter lower threshold

value.

Syntax :PMETer:THReshold:LOWer {<NRf>}

<NRf> = -70.00 to 5.00 (in steps of 0.001) [dBm]

Example : PMETER: THRESHOLD: LOWER -70.00

:PMETER:THRESHOLD:LOWER?

-> :PMETER:THRESHOLD:LOWER -70.00

IM AQ1100-17EN 4-11

:PMETer:THReshold:UPPer

Function Sets or queries the power meter upper threshold

value.

Syntax :PMETer:THReshold:UPPer {<NRf>}

< NRf > = -70.00 to 5.00 (in steps of 0.001) [dBm]

Example : PMETER: THRESHOLD: UPPER -70

:PMETER:THRESHOLD:UPPER?

-> :PMETER:THRESHOLD:UPPER -70

:PMETer:UNIT

Function Sets or queries the power meter display unit.

Syntax : PMETer:UNIT {DB|DBM|W}

:PMETer:UNIT ?

Example : PMETER: UNIT DBM

:PMETER:UNIT ? -> :PMETER:UNIT DB

:PMETer:WAVelength:DETail

Function Sets or queries the wavelength when the wavelength

mode is set to Detail.

Syntax :PMETer:WAVelength:DETail {<NRf>}

:PMETer:WAVelength:DETail? <NRf> = 0.850um to 1.650um (850E-9 to 1650E-9)

Example : PMETer: WAVELENGTH: DETAIL 0.85um

:PMETer:WAVELENGTH:DETAIL 1650E-9 :PMETer:WAVELENGTH:DETAIL 1.650E-6

:PMETer:WAVELENGTH:DETAIL?

-> PMETER:WAVELENGTH:DETAIL 1550E-09

Description If the wavelength mode is set to Simple or CWDM,

executing this command sets the mode to Detail.

:PMETer:ZERoset

Function Executes zero set on the power meter.

Syntax : PMETer: ZERoset
Example : PMETER: ZEROSET

4-12 IM AQ1100-17EN

4.8 PON Group

The commands in this group deal with the power meter. These commands are valid when the PON option is selected. You can make the same settings and queries that you can by using the front panel.

: PON: AVERage: TIMes

Function Sets or queries the PON power meter average

count.

Syntax :PON:AVERage:TIMes <T1|T10|T50|T100>

:PON:AVERage:TIMes?

Example : PON:AVERAGE:TIMES

:PON:AVERAGE:TIMES? -> :PON:AVERAGE:

TIMES T1

:PON:DIRection

Function Sets or queries the PON power meter wavelength.

Syntax : PON:DIRection {ONT2OLT|OLT2ONU}

Example : PON: DIRECTION ONT2OLT

:PON:DIRECTION?

-> :PON:DIRECTION ONT2OLT

: PON:M1310:MEASurement:DATA?

Function Queries the measured results of the 1310 nm PON

power meter.

Syntax :PON:M1310:MEASurement:DATA?

Example :PON:M1310:MEASUREMENT:DATA?

-> : PON:M1310:MEASUREMENT:DATA

: PON: M1310: OFFSet

Function Sets or queries the 1310 nm PON power meter

offset.

Syntax :PON:M1310:OFFSet {<NRf>}

<NRf> = -9.900 to 9.900 (in steps of

0.001)

Example :PON:M1310:OFFSET -9.900

:PON:M1310:OFFSET?

-> :PON:M1310:OFFSET -9.900

: PON: M1310: THReshold: JUDGe?

Function Queries the threshold judgment results of the 1310

nm PON power meter.

Syntax : PON:M1310:THReshold:JUDGe?
Example : PON:M1310:THRESHOLD:JUDGE?

-> :PON:M1310:THRESHOLD:JUDGE FAIL

Description A result of PASS or FAIL is returned.

:PON:M1310:THReshold:LOWer

Function Sets or queries the lower threshold value of the 1310

nm PON power meter.

Syntax :PON:M1310:THReshold:LOWer {<NRf>}

< NRf > = -70.00 to 5.00 (in steps of 0.001) [dBm]

Example :PON:M1310:THRESHOLD:LOWER -70.00

:PON:M1310:THRESHOLD:LOWER?

-> :PON:M1310:THRESHOLD:LOWER -70.00

:PON:M1310:THReshold:UPPer

Function Sets or queries the upper threshold value of the

1310 nm PON power meter.

Syntax :PON:M1310:THReshold:UPPer {<NRf>}

< NRf > = -70.00 to 5.00 (in steps of 0.001) [dBm]

Example :PON:M1310:THRESHOLD:UPPER -70.00

:PON:M1310:THRESHOLD:UPPER?

-> :PON:M1310:THRESHOLD:UPPER -70.00

: PON: M1490: MEASurement: DATA?

Function Queries the measured results of the 1490 nm PON

power meter.

Syntax : PON:MEASurement:DATA?

Example : PON:MEASUREMENT:DATA?

-> :PON:MEASUREMENT:DATA -26.5

:PON:M1490:OFFSet

Function Sets or queries the 1490 nm PON power meter

offset.

Syntax :PON:M1490:OFFSet {<NRf>}

 $\langle NRf \rangle = -9.900$ to 9.900 (in steps of

0.001)

Example :PON:M1490:OFFSET -9.900

:PON:M1490:OFFSET?

-> :PON:M1490:OFFSET -9.900

: PON: M1490: THReshold: JUDGe?

Function Queries the threshold judgment results of the 1490

nm PON power meter.

Syntax : PON:M1490:THReshold:JUDGe?
Example : PON:M1490:THRESHOLD:JUDGE?

-> :PON:M1490:THRESHOLD:JUDGE FAIL

Description A result of PASS or FAIL is returned.

:PON:M1490:THReshold:LOWer

Function Sets or queries the lower threshold value of the 1490

nm PON power meter.

Syntax : PON:M1490:THReshold:LOWer {<NRf>}

<NRf> = -70.00 to 5.00 (in steps of 0.001) [dBm]

Example :PON:M1490:THRESHOLD:LOWER -70.00 :PON:M1490:THRESHOLD:LOWER?

-> :PON:M1490:THRESHOLD:LOWER -70.00

IM AQ1100-17EN 4-13

:PON:M1490:THReshold:UPPer

Function Sets or queries the upper threshold value of the

1490 nm PON power meter.

Syntax :PON:M1490:THReshold:UPPer {<NRf>}

<NRf> = -70.00 to 5.00 (in steps of 0.001) [dBm] :PON:UNI

Example :PON:M1490:THRESHOLD:UPPER -70.00

:PON:M1490:THRESHOLD:UPPER?

-> :PON:M1490:THRESHOLD:UPPER -70.00

:PON:M1550:MEASurement:DATA?

Function Queries the measured results of the 1550 nm PON

power meter.

Syntax : PON:M1550:MEASurement:DATA?

Example : PON:M1550:MEASUREMENT:DATA?

-> :PON:M1550:MEASUREMENT:DATA

:PON:M1550:OFFSet

Function Sets or queries the 1550 nm PON power meter

offset.

Syntax : PON:M1550:OFFSet {<NRf>}

< NRf > = -9.900 to 9.900 (in steps of

0.001)

Example :PON:M1550:OFFSET -9.900

:PON:M1550:OFFSET?

-> :PON:M1550:OFFSET -9.900

:PON:M1550:THReshold:JUDGe?

Function Queries the threshold judgment results of the 1550

nm PON power meter.

Syntax : PON:M1550:THReshold:JUDGe?
Example : PON:M1550:THRESHOLD:JUDGE?

-> :PON:M1550:THRESHOLD:JUDGE FAIL

Description A result of PASS or FAIL is returned.

:PON:M1550:THReshold:LOWer

Function Sets or queries the lower threshold value of the 1550

nm PON power meter.

Syntax : PON:M1550:THReshold:LOWer {<NRf>}

< NRf > = -70.00 to 5.00 (in steps of

0.001) [dBm]

Example :PON:M1550:THRESHOLD:LOWER -70.00

:PON:M1550:THRESHOLD:LOWER?

-> :PON:M1550:THRESHOLD:LOWER -70.00

:PON:M1550:THReshold:UPPer

Function Sets or queries the upper threshold value of the

1550 nm PON power meter.

Syntax :PON:M1550:THReshold:UPPer {<NRf>}

 $\langle NRf \rangle = -70.00$ to 5.00 (in steps of

0.001) [dBm]

Example : PON:M1550:THRESHOLD:UPPER -70.00

:PON:M1550:THRESHOLD:UPPER?

-> :PON:M1550:THRESHOLD:UPPER -70.00

: PON: UNIT

Function Sets or queries the PON power meter display unit.

Syntax : PON:UNIT {DBM|W}
Example : PON:UNIT DBM

:PON:UNIT ? -> :PON:UNIT DBM

: PON: ZERoset

Function Executes zero set on the PON power meter.

Syntax : PON: ZERoset
Example : PON: ZEROSET

4-14 IM AQ1100-17EN

4.9 PRINt Group

The commands in this group deal with printing. You can make the same settings and queries that you can by using the front panel.

:PRINt:COLor

Function Sets or queries the print colors.

Syntax :PRINt:COLOr {COLOR | BW}

:PRINt:COLor?

Example :PRINT:COLOR COLOR

:PRINT:COLOR? -> :PRINT:COLOR BW

Description Screen colors: COLOR

Black and white: BW

:PRINt:EXECute

Function Executes printing.

Syntax :PRINT:EXECUTE

Example :PRINT:EXECUTE

:PRINt:MAKer

Function Sets or queries the printer manufacturer.

Syntax : PRINt:MAKer {HP|EPSON|SEIKO}

:PRINt:MAKer?

Example : PRINT: MAKER HP

:PRINT:MAKER?

-> :PRINT:MAKER EPSON

Description HP inkjet printer: HP

EPSON inkjet printer: EPSON Seiko Instruments MPU-L465: SEIKO

IM AQ1100-17EN 4-15

4.10 SETup Group

The commands in this group deal with the initialization of the settings. This instrument settings can be returned to their factory defaults.

:SETup:INITialize

Function Returns all settings to their factory defaults.

Syntax :SETup:INITialize
Example :SETUP:INITIALIZE

4-16 IM AQ1100-17EN

4.11 STATus Group

The commands in this group are used to make settings and queries related to the communication status feature. There are no front panel keys that correspond to the commands in this group.

:STATus?

Function Queries all the settings for the communication status

feature.

Syntax :STATus?

Example :STATUS? -> :STATUS:QENABLE1;

QMESSAGE 1

:STATus:CONDition?

Function Queries the contents of the condition register.

Syntax :STATus:CONDition?
Example :STATUS:CONDITION? -> 16

Description For information about the condition register, see

section 5.1, "Condition Register."

:STATus:ERRor?

Function Queries the error code and message information (top

of the error queue).

Syntax :STATus:ERRor?

Example :STATUS:ERROR? ->113,"Undefined header"

:STATus:QENable

Function Sets or queries whether or not messages other than

errors will be stored to the error queue (on/off).

Syntax :STATus:QENable {<Boolean>}:STATus:

QENable?

Example :STATUS:QENABLE ON

:STATUS:QENABLE? -> :STATUS:QENABLE 1

:STATus:QMESsage

Function Sets or queries whether or not message information

will be attached to the response to the STATus:

ERRor? query (on/off).

Syntax :STATus:QMESsage {<Boolean>}

:STATus:QMESsage?

Example :STATUS:QMESSAGE OFF

:STATUS:QMESSAGE? -> :STATUS:QMESSAGE 1

IM AQ1100-17EN 4-17

4.12 SYSTem Group

The commands in this group deal with startup. There are no front panel keys that correspond to the commands in this group.

:SYSTem:REBoot

Function Restarts this instrument.

Syntax :SYSTem:REBoot

Example :SYSTEM:REBOOT

:SYSTem:SHUTdown

Function Shuts down this instrument.

Syntax :SYSTem:SHUTdown

Example :SYSTEM:SHUTDOWN

4-18 IM AQ1100-17EN

4.13 VLS Group

The commands in this group deal with the visible light source. These commands are valid when the VLS option is selected. You can perform the same operations and make the same settings and queries that you can by using the front panel.

:VLS:ABORt

Function Turns the visible light source off.

Syntax :VLS:ABORt
Example :VLS:ABORT

:VLS:EXECute

Function Turns the visible light source on.

Syntax :VLS:EXECute
Example :VLS:EXECUTE

IM AQ1100-17EN 4-19

4.14 Common Commands

*CLS (Clear Status)

Function Clears all event status registers that are displayed in

the status byte register summary.

Syntax *CLS
Example *CLS

 $\label{eq:Description} \bullet \ \ \text{Clears all queues except the output queue and}$

all event registers except the MAV summary

message.

 After this command is executed, this instrument is set to OCIS (Operation Complete Command Idle State) and OQIS (Operation Complete Query Idle

State).

*ESE (Standard Event Status Enable)

Function Sets or queries the standard event enable register.

Syntax *ESE<wsp><integer>

*ESE?

<integer> = 0 to 255

Example *ESE 251

*ESE? -> 251

Description • Each item whose bit is set is enabled.

The ESE is set to its default value when:

The power is turned on.

Zero is set.

The ESE does not change its value when the

following commands are executed:

*RST *CLS

Device clear (DCL, SDC)

• The default value is zero.

*ESR? (Standard Event Status Register)

Function Queries and clears the standard event status

register.

Syntax *ESR?

Example *ESR? -> 251

Description The returned value of this query is not affected by

the ESE (Event Status Enable Register).

*IDN? (Identification)

Function Queries the instrument type and firmware version.

Syntax *IDN

Example *IDN? -> YOKOGAWA, AQ1100, SN123456789,

F1.00

Description Four data fields delimited by commas are returned.

Field 1: Manufacturer "YOKOGAWA" Field 2: Model "AQ1100"

Field 3: Instrument serial number

"SN123456789"

Field 4: Firmware version "F1.00"

*OPT? (Option)

Function Queries the option information.

Syntax *OPT?

Example *OPT? -> PM, LS, LAN

Description The installed options are returned delimited by

commas.

Power meter: PM
Light source: LS
Visible light source: VLS
LAN: LAN

*RST (Reset)

Function Returns all the settings except the communication

settings to their factory default values.

Syntax *RST Example *RST

Description • This command stops the operation in progress

and resets this instrument to its factory defaults.

• The following items do not change:

Output queue

SRE

Calibration data that affects this instrument

specifications

4-20 IM AQ1100-17EN

*SRE (Service Request Enable)

Function Sets or queries the service request enable register.

Syntax *SRE <wsp><integer>

*SRE?

<integer> = 0 to 255

*SRE 250 Example

*SRE? -> 250

Description • Each item whose bit is set is enabled.

• The SRE is set to its default value when:

The power is turned on.

Zero is set.

· The SRE does not change its value when the following commands are executed:

*RST

*CLS

Device clear (DCL, SDC)

· The default value is zero.

*STB? (Read Status Byte)

Function Queries the current status byte register value.

Syntax

*STB?

*STB? -> 251 Example

Description The STB is not cleared even if it is read.

*TST? (Self Test)

Function Executes a self-test.

Syntax *TST? Example *TST? -> 0

Description This instrument returns 0 if the self-test is successful

and 1 if it is not.

4-21 IM AQ1100-17EN

5.1 **Condition Register**

The condition register indicates the internal condition of the instrument.

Condition Register	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
:STATus:CONDition?	0	0	0	0	LS	PME	PMZ	РММ	0	AR	0	FIA	0	FILE	0	0

The meaning of each bit of the condition register is as follows:

Bit 2	FILE	Set to 1 while a file is being accessed.
Bit 4	FIA	Set to 1 while checking whether the fiber is in use.
Bit 6	AR	Set to 1 while the auto range measurement is in progress.
Bit 8	PMM	Set to 1 while the power meter measurement is in progress.
Bit 9	PMZ	Set to 1 while the power meter is being reset to zero.
Bit 10	PME	Set to 1 while a measurement error is occurring in the power meter.
Bit 11	LS	Set to 1 while the light source is ON.


5-1 IM AQ1300-17EN

5.2 Output and Error Queue

Output Queue

The output queue stores query response messages. As shown below, data is stored in order and read from the oldest message first. The output queue is cleared when this instrument is turned off and then back on.

The output queue cannot be emptied using the *CLS command. To see whether the output queue is emptyor not, check bit 4 (MAV) of the status byte.



Error Queue

When an error occurs, the error queue stores the error number and message. For example, if this instrument receives an incorrect program message from the controller, the error number (113) and the error message ("Undefined header") are stored in the error queue when this instrument displays the error message.

You can use the :STATus:ERRor? query to read the contents of the error queue. Like the output queue, the messages in the error queue are read from the oldest one first.

If the error queue overflows, the last message is replaced with the following message: 350, "Queue overflow"

The error queue is cleared when:

- A *CLS command is received.
- · This instrument is turned off and then back on.

You can determine whether or not the error queue is empty by checking bit 2 in the status byte (EAV).

5-2 IM AQ1300-17EN

Error Messages Appendix

This section explains communication error messages.

- Messages can be displayed in English or in another language on this instrument. However, when they are read from a PC or other similar device, messages are displayed in English.
- If servicing is necessary to solve the problem indicated by a message, contact your nearest YOKOGAWA dealer.
- · Only communication error messages are listed here. For other error messages, see the User's Manual IM AQ1100-01EN.

Error in Execution

Code	Message
50	*OPC/? exists in message.
102	Syntax error.
103	Invalid separator.
104	Data type error.
108	Parameter not allowed.
109	Missing parameter.
111	Header separator error.
112	Program mnemonic too long.
113	Undefined header.
114	Header suffix out of range.
120	Numeric data error.
123	Exponent too large.
124	Too many digits.
128	Numeric data not allowed.
131	Invalid suffix.
134	Suffix too long.
138	Suffix not allowed.
141	Invalid character data.
144	Character data too long.
148	Character data not allowed.
150	String data error.
151	Invalid string data.
158	String data not allowed.
161	Invalid block data.
168	Block data not allowed.
171	Invalid expression.
178	Expression data not allowed.
181	Invalid outside macro definition.
221	Setting conflict.
222	Data out of range.
223	Data invalid
224	Illegal parameter value.
241	Hardware missing.
260	Expression error.
270	Macro error.
272	Macro execution error.
273	Improper macro label.
275	Macro definition too long.
276	Macro recursion error.
277	Macro redefinition not allowed
278	Macro header not found.
350	Queue overflow.
410	Query INTERRUPTED.
420	Query UNTERMINATED.
430	Query DEADLOCKED.
440	Query UNTERMINATED after indefinite response.

IM AQ1300-17EN App-1

Index

Index

Symbol
<boolean> 3-7</boolean>
Character Data> 3-7
<decimal> 3-6</decimal>
<distance></distance>
<loss></loss>
<multiplier></multiplier>
<pmt></pmt>
<program message="" unit=""></program>
<rmt></rmt>
<string data=""></string>
<time> 3-6</time>
<unit></unit>
<wavelength> 3-6</wavelength>
Svavelength/ 3-0
<u>A</u>
Abbreviated Form
average count
C
Command
Common Command
COMMunicate Group 4-4
communication status feature 4-17
Compound Header 3-3
Condition Register 4-17, 5-1
D Data
DHCP 4-9
display unit (pon power meter's) 4-14
display unit (power meter's) 4-12
Dref
F
<u>E</u>
error code and message information 4-17
error dialog box
Error Messages App-1
Error Queue
Ethernet Interface 2-2
Ethernet on/off state
Executes printing 4-15
LikeCutes printing
<u>F</u>
factory default
firmware version
function mode 4-6
6
G
gateway
Н
Header 3-1, 4-4
1
<u>1</u>
ID address 4.0

ight off	1.5
•	4-19
ight on	
ight on (visible light source)	
LIGHtsource Group	
ight source power meter setting interlock	
ower threshold value (pon power meter's)	
ower threshold value (power meter's)	
VI	
	4 44
MAX neasured results (pon power meter's)	
neasured results (poir power meter's)	
neasurement light	
MENU Group	
Messages	
Wessage Unit	
Vicesage Office	
mini B	
VISC Group	
modulation	
modulation frequency	
4	
N	
NETWork Group	4-9
0	
offset (pon power meter's)	1 13
offset (power meter's)	
option information	
Output Queue	
Sutput Queue	J-Z
P	
password	
PMETer Group	
PMT	
PON Group	
Port number	
	4-15
· · · · · · · · · · · · · · · · · · ·	4-15
	4-15
Program Messages	3-1
Q	
query	3-1
R	
reference value	4-11
Releasing the Remote Control (Ethernet)	
Releasing the Remote Control (USB)	
Response Data	
	4-18
DIAT.	0.4

Index

self-test	4-21
service request enable register	4-21
SETup Group	4-16
shortest abbreviation	3-4
Shuts down	4-18
standard event enable register	4-20
standard event status register	4-20
status byte register 4-20,	4-21
STATus Group	4-17
STP cable	2-3
subnet mask	4-10
Switching from Local to Remote Mode (Ethernet)	
Switching from Local to Remote Mode (USB)	
Switching from Remote to Local Mode (Ethernet)	
Switching from Remote to Local Mode (USB)	
SYSTem Group	4-18
т	
TCP/IP	
threshold judgment results	
Timeout Value	
type B	1-3
U	
Upper-level Query	3-3
upper threshold value (pon power meter's)	4-13
upper threshold value (power meter's)	4-12
USB connector type B (mini B)	1-3
USB Interface	1-2
user name	4-9
UTP cable	2-3
V	
VLS Group	4-19
W	
wavelength (pon power meter's)	
wavelength (power meter's)	
wavelength mode (power meter's)	4-12
Z	
zero set (pon power meter's)	4-14
	4-12

Index-2